



Installation and operation of the Wiztec SMS messaging system.

Wiztec Business Solutions

Using Wiztec applications

The routine described in this guide is furnished under a license agreement and may be used only in accordance with the terms of that agreement

Copyright Notice

Copyright © 2005 - 2020 Wiztec Ltd. All rights reserved

No part of this document may be copied without the express written permission of Wiztec Ltd., Unit 14, Airport East Technology & Business Park, Farmers Cross, Cork.

Trademarks

Windows is a trademark of Microsoft Corporation. Other product names mentioned in this guide may be trademarks or registered trademarks of their respective companies and are hereby acknowledged

About this guide

This guide was produced for assistance in using Wiztec's messaging system.

Although Wiztec Ltd has tested the software and reviewed the documentation, Wiztec makes no warranty or representation, either express or implied, with respect to this software or documentation, their quality, performance, merchantability or fitness for a particular purpose. This software and documentation are licensed 'as is', and you, the licensee, by making use thereof, are assuming the entire risk as to their quality and performance.

In no event will Wiztec Ltd be liable for direct, indirect, special, incidental or consequential damages arising out of the use or inability to use the software or documentation.

Support:

Support for this software is available from support@wiztec.ie or by calling the Wiztec Help desk on 021 4316881

Disclaimer:

Wiztec's policy is one of constant development and improvement. We reserve the right to alter, modify, correct and upgrade our software program and publications without notice and without incurring liability.

Issue Date: 28/10/2019
Document Number: Wizsms-1.1DOC
Program compile date: na



Setting up sms

A. Connecting the 4G modem device

1. Connect the device to a serial port on your P/C. If you don't have a serial port connect it using the convertor to a USB port. Check the device has power.
2. Reboot your PC to complete installation of drivers. IT MUST BE REBOOTED..
3. Verify in device manager that the unit has been install and the comport that it is using.


B. Install

1. Download <http://www.wiztec.ie/downloads/wizsms.zip>
2. Unzip to the same directory where the .exe you wish it to operate with is located. E.G if you have the membership system right click and take properties and this will show you the directory where the membership.exe is located. Copy the sms.exe to that directory.



C. Unit tester

1. Run unit tester




2. Select Com port this must match the port the unit is connected to.
3. Click open
4. You will be asked to power the unit off and on to test it
5. Make a note of the Baud rate




D. Com port tester


1. Run Com_tester
2. Click settings



3. Fill in the comport and baud rate
4. Click OK
5. Click Store (Centre of screen)



6. Enter in your number in the bottom left
7. click send test message
8. Reply to message
9. Click Get Unread



This is the NUMBERS screen when you run the sms.exe

It shows a list off all the members and their numbers and from here you can select people if you just want to send a once off message. Type the message on the RH side , select who its to go to and hit send.

The next screen is Waiting mode. The unit should be left in this mode when not in use to send messages as in this mode it will respond to incoming messages.

If you wish to tell the people youre sending to that if they don't wish to receive any further messages then when they receive your message they would just reply with Stop and this will blacklist them and no further messages will go to them.

The BLACKLIST icon will show who is on the list as above

The GROUPS icon allows you to create groups who you may want to send specific texts to.

From your mobile if you reply to the SMS text number with the following command a message will be sent from it to the group as if you were running it from the s/w.

Group [group name] and message so if we had a group called cyclists and you were going to be 15 mins late for a session from your mobile you would send a message to the sms s/w as follows :




Group cyclists I am gonna be 15 mins late, please wait for me. Anybody in that group will then receive the message I am gonna be 15 mins late, please wait for me. The s/w must be in waiting mode for this to operate.

The most important feature in the software is the ability to send auto texts with specified messages to members or groups.




Click on the auto sms icon.

SMS Templates
✕

Template	Condition	Active	Code Access	Committee	Contractor	Gym	Inactive	Inactive - No Contact	Pending Member
sorry to loose you	Expiring	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Membership	Expiring	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Membership Expired	Expired	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>






Create and edit Current Templates


Hit the + button to create a template.
Enter a Name for it and the text for the message.





Click the save button

Hit the green + button on the LH side. This is where we create the condition for the message to be sent .




Next select the template to be sent when that condition is met. In this case its when membership is expired today.

Leave the s/w in waiting mode and as required the messages will be sent.

Setup task scheduler as follows to schedule the emails :


Go to control panel >> administrative tools >>>> Task scheduler >> On the RH Side select create task





On the general tab enter the name Auto SMS TXT

On the Triggers select how often you wish to run it :



Edit Trigger

Begin the task: On a schedule

Settings

☐ One time

☒ Daily

☐ Weekly

☐ Monthly

Start: 27/02/2020 09:09:23 ☐ Synchronize across time zones

Recur every: 1 days

Advanced settings

☐ Delay task for up to (random delay): 1 hour

☐ Repeat task every: 1 hour for a duration of: 1 day

☐ Stop all running tasks at end of repetition duration

☐ Stop task if it runs longer than: 3 days

☐ Expire: 27/02/2021 12:19:54 ☐ Synchronize across time zones


☒ Enabled

OK Cancel

On the example above we are running it daily at 09.09 . Enter the time you wish to run it at. If you wished to run the task more than once a day select repeat task every option.



Next you select the action tab.



PLEASE NOTE THE PROGRAM/SCRIPT PATH MUST BE THE PATH WHERE THE SMS.EXE IS LOCATED.

ADD THE ARGUMENT -autosms

Select OK or save.

This will then run automatically even if the sms software is closed down.

Any questions please contact support@wiztec.ie or phone 021-4316881

